

E36200 Series Power Supply

Version 1.0.6_1.0.3_1.01 Information

Released Date:	16 May 2024
Requirements category (e.g., operating system):	Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10
File Name:	E3623X_1.0.6_1.0.3_1.01.dfu

Bug Fixes

- Fixed 30V units cannot output more than 20A issue

Version 1.0.4_1.0.3_1.00 Information

Released Date:	15 Jul 2022
Requirements category (e.g., operating system):	Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10
File Name:	E3623X_1.0.4_1.0.3_1.00.dfu

Bug Fixes

- *PSC 0 will set OUTPUT[:STATe]:COUPLE:CHANnel to NONE
- Fixed the status byte not set using LAN interface
- Fixed voltage spike issue after CC mode
- Resolved instrument boot up issue.

Version 1.0.3_1.0.2_1.00 Information

Released Date:	30 Nov 2021
Requirements category (e.g., operating system):	Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10
File Name:	E3623X_1.0.3_1.0.2_1.00.dfu

Enhancement

- Added the model ID into USB descriptor to allow the USB connection through gateway

Version 1.0.2_1.0.2_1.00 Information

Released Date:	17 Aug 2021
Requirements category (e.g., operating system):	Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10
File Name:	E3623X_1.0.2_1.0.2_1.00.dfu

Enhancement

- Supports E36231A, E36232A, E36233A, E36234A
- Fixed current readback fluctuation at front panel

